

ZKTeco License Activation Software User Manuel

ZKTeco License Activation Software is suitable for all ZKiVision software with face identification function.

Before using this software, please make sure that the USB dongle has been connected with PC.


ZKTeco USB dongle is suitable for all PC with USB interface. It can communicate with PC through USB.

This software is only for activating License. If want to use the complete function of face identification, please refer to ZKiVision software user manual.


Start the Activation Software

This activation software is in the form of ZIP file, which can be got from ZKTeco. Before use, please make sure WINRAR or WINZIP software have been installed in your PC.

After start-up, the software will detect automatically whether there is an USB dongle connected in PC as below picture:




If no USB dongle has been detected, wrong information will be displayed as below picture:



Here, you can click "Try" button to start re-detection, or click the close button in top right corner to close this software, and check whether the USB dongle is connecting well.


Run Activation

If an USB dongle is detected by the activation software, below notification will be displayed:




If you want to activate the USB dongle, please click "Next". If not, please click "Back" and withdraw the software.

If you choose activate the USB dongle, below information will be displayed:



After waiting for a while, activation result will be showed in the screen. If succeed, below information will be displayed:



😊 Notes:

- 1) Please close ZKiVision software then activate the license.
- 2) Please disable the face function in ZKiVision software before unplug the USB dongle.
- 3) If license activation is not successful, may the following two reasons:
 - a) The dongle service program is intercepted by security software -- Please shut down the security software.
 - b) Windows 2007 operating system access to the license activation software is not successful, Please right click the activation software and choose "Run as administrator".